مشکل عدم باز شدن internet Explorer و باز شدن edge به جای آن

رفع مشکل عدم باز شدن چارگون در edge

اگر موقع باز کرد IE به جای آن edge باز می شود و مشکلی مطابق تصویر زیر در باز شدن چارگون ایجاد شد. مراحل زیر را برای رفع مشکل انجام دهید.

۱- از بالا سمت راست روی سه نقطه کلیک کنید.



۲- از منوی باز شده وارد settings شوید



۳- روی سه خط سمت چپ کلیک کنید

۴- Default browser کلیک کنید.

	2 🗖 🖉	🔁 Didgah 🛛 🗙	段3 Settings	× +			—	ð	\times
٣	< C	€ Edge edge://settings/profi	iles		2 CD 2	`⊨ (⊕	~~		
	Settings r	ings ^{menu}			Q Search settings				
	8	Profiles							
	÷ •	Privacy, search, and services			+ Add	profile			
	4)	Appearance			C				
		Sidebar	-		0-				
		Start, home, and new tabs							
		Share, copy and paste	and see your favorites passwords	histony and more on all					
۲		Cookies and site	itement	nistory, and more on an	your				
		Default browser							
	<u> </u>	Downloads	Sign in to sync data						
	양 F	Family safety							
	At 1	Languages							
		Printers							
		System and performance				>			
	5	Reset settings							
	_ F	Phone and other devices			Go to Settin	vvindow gs to activ	VS /ate Win		
	*	Accessibility				>			
	📰 🔎 Ту	ype here to search	H 🗢 🥭 🕚	🗖 📀 💽	👯 🥌 48°F	~ 도 6	09:371	ق.خ 1•/•1	1

۵- اگر در قسمت Internet Explorer mode pages ادرس چارگون (۱۹۲,۱۶۸,۱۰۰,۱۳) اضافه نشده بود می بایست
 ۱۹۲,۱۶۸,۱۰۰,۱۳ این ادرس را با زدن دکمه Addاضافه کنید.

*	Image: Didgah X Settings X + C Tedge edge://settings/defaultBrowser	。 - 。 - · · · · · · · · · · · · · · · · · · ·
=	Settings	Q Search settings
	Default browser	
	Microsoft Edge is your default browser	Make default
	Allow sites to be reloaded in Internet Explorer mode (IE mode) ⑦ When browsing in Microsoft Edge, if a site requires Internet Explorer for compatibility, you can choos	Allow 🗸
	Allow sites to be reloaded in Internet Explorer mode (IE mode) ⑦ When browsing in Microsoft Edge, if a site requires Internet Explorer for compatibility, you can choos Internet Explorer mode pages These names will open in Internet Explorer mode for 30 days from the date you add the page. No page	Allow ✓ e to reload it in Internet Explorer mode Add
	Allow sites to be reloaded in Internet Explorer mode (IE mode) ③ When browsing in Microsoft Edge, if a site requires Internet Explorer for compatibility, you can choos Internet Explorer mode pages These pages will open in Internet Explorer mode for 30 days from the date you add the page. No pag mode list yet.	Allow e to reload it in Internet Explorer mode Add es have been added to the Internet Explorer
_	Allow sites to be reloaded in Internet Explorer mode (IE mode) ③ When browsing in Microsoft Edge, if a site requires Internet Explorer for compatibility, you can choos Internet Explorer mode pages These pages will open in Internet Explorer mode for 30 days from the date you add the page. No pag mode list yet. Internet Options	Allow ✓ e to reload it in Internet Explorer mode Add es have been added to the Internet Explorer
_	Allow sites to be reloaded in Internet Explorer mode (IE mode) ③ When browsing in Microsoft Edge, if a site requires Internet Explorer for compatibility, you can choos Internet Explorer mode pages These pages will open in Internet Explorer mode for 30 days from the date you add the page. No pag mode list yet. Internet Options	Allow ✓ e to reload it in Internet Explorer mode Add es have been added to the Internet Explorer [2] Activate Windows Go to Settings to activate Windo

🔮 🗖 🐉 Didgah 🛛 🗙 🗙	段 Settings	× +						-	ð	×
← C	ultBrowser			☆	Cþ	£≞	Ē	~~		•
≡ Settings			Q	Search s	ettings					
Default browser										
Microsoft Edge is your default browser					Make	default				
F Internet Explorer compatibil Allow sites to be reloaded in Internet When browsing in Microsoft Edge, if a site re	Add a page Enter a URL: \\192.168.100.13		×	net Explor	Allor	N V				
Internet Explorer mode pages These pages will open in Internet Explorer mode mode list yet.	Add	Cancel		to the Int	ernet Exp	Add				
Internet Options						C	3			
				Ad	ctivat to Sei	e Wir tings ti	ndow. o activ	09-37	ndows	

 ۷- در ادامه پس از اضافه شدن ادرس چارگون روی Internet Options کلیک کرده و وارد تنظیمات اینترنت اکسپلورر شوید.

E Settings Default browser \\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\	÷	C C Edge edge://settings/defaultBrowser		\$ CD	£ @	<i>~</i> ~	
Default browser Microsoft Edge is your default browser Make default Internet Explorer compatibility Wen browsing in Microsoft Edge, if a site requires Internet Explorer for compatibility, you can choose to reload it in Internet Explorer mode Internet Explorer mode page Internet Explorer mode page Internet Explorer mode for 30 days from the date you add the page. You have 1 page that"Il automatically open in Internet Page Date added Explorer Date added Explorer	=	Settings		Q Search settings			
Microsoft Edge is your default browser Make default Internet Explorer compatibility Internet Explorer mode (IE mode) ⑦ Allow ✓ When browsing in Microsoft Edge, if a site requires Internet Explorer for compatibility, you can choose to reload it in Internet Explorer mode Allow ✓ Internet Explorer mode pages Add These pages will open in Internet Explorer mode for 30 days from the date you add the page. You have 1 page that'll automatically open in Internet Explorer mode. Date added Expires Page Date added Expires Add		Default browser		'\\192.168.100.13' adde	ed ×		
Internet Explorer compatibility Allow sites to be reloaded in Internet Explorer mode (IE mode) ⑦ When browsing in Microsoft Edge, if a site requires Internet Explorer for compatibility, you can choose to reload it in Internet Explorer mode Internet Explorer mode pages Add These pages will open in Internet Explorer mode for 30 days from the date you add the page. You have 1 page that'll automatically open in Internet Explorer mode. Page Date added Expires		Microsoft Edge is your default browser		Make	default		
These pages will open in Internet Explorer mode for 30 days from the date you add the page. You have 1 page that'll automatically open in Internet Explorer mode. Page Date added Expires		Internet Explorer compatibility Allow sites to be reloaded in Internet Explorer mode When browsing in Microsoft Edge, if a site requires Internet Exp	(IE mode) ⑦	Allor bad it in Internet Explorer mode	w ~		
Page Date added Expires		Internet Explorer compatibility Allow sites to be reloaded in Internet Explorer mode When browsing in Microsoft Edge, if a site requires Internet Exp Internet Explorer mode pages	(IE mode) ⑦	Allor oad it in Internet Explorer mode	w ×		
		Internet Explorer compatibility Allow sites to be reloaded in Internet Explorer mode When browsing in Microsoft Edge, if a site requires Internet Exp Internet Explorer mode pages These pages will open in Internet Explorer mode for 30 days from Explorer mode.	(IE mode) ⑦ Jorer for compatibility, you can choose to relo om the date you add the page. You have 1 pag	Allor oad it in Internet Explorer mode ge that'll automatically open in I	w v Add Internet		
		Internet Explorer compatibility Allow sites to be reloaded in Internet Explorer mode When browsing in Microsoft Edge, if a site requires Internet Explorer mode Internet Explorer mode pages Intese pages will open in Internet Explorer mode for 30 days from Explorer mode. Page Internet file://192.168.100.13/	(IE mode) ⑦ olorer for compatibility, you can choose to rele om the date you add the page. You have 1 pag Date added 11/22/2023	Allor oad it in Internet Explorer mode ge that'll automatically open in I Expires 12/22/2023	w v Add Internet		
Internet Options	_	Internet Explorer compatibility Allow sites to be reloaded in Internet Explorer mode When browsing in Microsoft Edge, if a site requires Internet Exp Internet Explorer mode pages These pages will open in Internet Explorer mode for 30 days fro Explorer mode. Page These file://192.168.100.13/ Internet Options	(IE mode) ⑦ olorer for compatibility, you can choose to relo om the date you add the page. You have 1 pag Date added 11/22/2023	Allor bad it in Internet Explorer mode ge that'll automatically open in I Expires 12/22/2023	W V Add Internet		

۸- در تب securityروی قسمت Trusted sites کلیک کنید.

۹- سپس روی Custom level کلیک کنید تا پنجره ای مطابق تصویر بعدی باز شود.

🗖 😢 Didgah 🛛 🗙 🛱 Settings	× +			-	Ō
Internet Properties ? X		ሰ 🖒	Ē	~~	
General Security Privacy Content Connections Programs Advanced		Q Search settings			
Internet Local intrane Trusted sites Restricted sites Trusted sites Trusted sites Trust not to damage your computer or your files.		Make default			
Convint lovel for this man	-				
Allowed levels for this zone: All - Hedium - Prompts before downloading potentially unsafe content - Unsigned ActiveX controls will not be downloaded					
able Protected Made (sequises contacting internet Explorer) Custom level Default level	ode) ⑦ vr compatibility, you can choose to reload	Allow 🗸 it in Internet Explorer mode			
Reset all zones to default level	date you add the page. You have 1 page t	Add			
OK Cancel Apply	Date added	Expires			
b file://192.168.100.13/	11/22/2023	12/22/2023	Û		
Internet Options		C	3		
		Activate Wil Go to Settings t	ndow to activa	s ate Wir	ndov
ア Type here to search	🥭 🗊 🚍 👩 🗨 🖤	🔮 🤔 48°F 🔨	티	09:38	ق.ظ ۹/۰۱

در بیاورید. Enable از لیست باز شده عبارت زیر را پیدا کنید و آن را از حالت Disable به حالت Enableدر بیاورید. Initialize and script Active x controls not marked as safe....

Settinas					
J Dis	play video and animat	ion on a webpa	ge that do	es not use	^
	Disable				
	Enable wolcod cigood Activo	controlo			
	Disable	controis			
	Enable			l	-
	Promot				
	wnload unsigned Activ	eX controls			
	Disable				
ŏ	Enable				
•	Prompt				
	tialize and script Activ	eX controls not	marked as	safe for s	
	Disable				
۲	Enable				
	Prompt				-
4	lu allow approved don	aine to use Act	iveY witho	it prompt	
*Takas offe	et after you reatart ye				
Takes effe	ceanter you result yo	ar computer			
Reset custom	settings				
Reset to:	Medium (default)		-	Reset	
	includin (deroond)				_

۱۱-سپس عبارت زیر را پیدا کرده و آن را از حالت Enable به حالت Disable در آورید.

Use Pop-up Blocker

Internet Options ?	×
Security Settings - Trusted Sites Zone	×
Settings	
Enable Prompt	*
 Submit non-encrypted form data Disable 	
Enable Prompt	
Ose r op op blocker Ose r op op bloc	
 Disable Enable 	-
Takes effect after you restart your computer	
Reset custom settings	
Reset to: Medium (default) Reset	
OK Can	cel

- ۱۲ سپس دکمه OK را زده و پیام نمایش داده شده را نیز تایید نمایید .
- ۱۳- دوباره سه نقطه بالا سمت راست را کلیک کرده و روی عبارت زیر کلیک نمائید.

Reload in Internet Explorer mode



۱۴ منویی مطابق تصویر زیر باز می شود . دکمه های غیر فعال آن را فعال کرده و دکمه Done را بزنید. (هر دو دکمه باید به رنگ آبی باشد)



۱۵-تنظیمات به پایان می رسد . برنامه Edge را ببندید و دوباره باز کنید .